

Apple II File Type Notes



Developer Technical Support

File Type: **\$E2 (226)**
Auxiliary Type: **\$FFFF**

Full Name: EasyMount document
Short Name: EasyMount document

Written by: Dave Lyons

May 1992

Files of this type and auxiliary type contain EasyMount documents used by the System 6.0 EasyMount Finder extension.

The EasyMount Finder extension in System 6.0 creates EasyMount documents and uses them to let the user quickly connect to shared disks.

The File Format

An EasyMount document has the following format. In future versions, more data may be added to the end.

serverName	(+000)	String	Name of server to connect to.
entityName	(+xxx)	String	Always "AFPServer". Immediately follows serverName.
zoneName	(+xxx)	String	Name of zone containing server. Immediately follows entityName.
volumeName	(+097)	28 Bytes	Name String of specific volume to use on the server. This field takes 28 bytes regardless of the length of the String .
userName	(+125)	32 Bytes	User name String to connect with. This field takes 32 bytes regardless of the length of the String .
serverPassword	(+157)	8 Bytes	Password to connect with (padded with trailing zero bytes; all zeros to connect as Guest).
volumePassword	(+165)	8 Bytes	Volume password (padded with trailing zero bytes). Most servers do not use volume passwords, and EasyMount always fills this field with zeros.

Note that the `userName` field is big enough for a 31-character user name (with length byte). Although 32-character user names are valid under AppleShare, EasyMount can't deal with them (for historical reasons).

Passwords are stored **unencrypted** in EasyMount documents; finding one with a saved password is the same as finding that user's password to the server. Please take appropriate security precautions if you save passwords in EasyMount documents.

Further Reference

- System 6.0 Documentation