Apple Writer][Reference Card

Commands using the CTRL key are shown as [ ].
All commands may be entered in upper or lower case.

EDITING

Command	Effect
ESC ESC	Cursor move mode:
I	up one line
J	left one character
K	right one character
M	down one line
E	up 12 lines
S	left 24 characters or one word
D	right 24 characters or one word
X	down 12 lines
<--	Deletes character(s)
-->	Retrieves character(s) deleted by <--
[B]	Moves cursor to file beginning; sets Data Line arrow to >
[C]	Automatic case change; cursor displays L or U
[D]	Changes direction of Data Line arrow
[E]	Moves cursor to file end; sets data line arrow to <
[F]/{text}/{replacement}/	Finds and deletes {text} and inserts {replacement}
[G]?{character}{text}	Defines glossary term
[G]{character}	Inserts text previously defined by {character}
[G]*	Deletes all glossary definitions in memory
[I]	Tabs to position set by [T]
[K]	Alpha lock; displays U on Data Line
[L]FILENAME,d#	Loads FILENAME into memory from diskette in drive #
[L]#/marker1/marker2/	Copies specified text segment from memory to cursor position
[L]FILENAME,d#\	Displays FILENAME on screen
[L]?,d#	Lists file names on diskette in drive #
[N]	Erases memory
[O]	DOS Commands Menu
[P]?	[P]rint/Program Commands Menu
[Q]	Additional Functions Menu
[R]	Replace edit mode
[S]FILENAME,d#	Saves memory contents under FILENAME on diskette in drive #
[T]	Tab set/clear/purge
[V]	Accepts CTRL characters as text entries; V appears on Data Line
[W]	Word delete or insert
[X]	Paragraph delete or insert
[Y]	Split screen enable/disable
[Z]	Enable/disable word wrap-around; Z on Data Line when enabled

PRINTING

Command	Effect	
[P]NP	Prints text currently in memory	
[P]CP	Continues printing	
[P]?	Displays print format options	Default Value:
LM{number}	Sets left margin to {number}	9
PM{number}	Indents/Outdents paragraph margin to {number}; value relative to "LM"	0
RM{number}	Sets right margin to {number}	79
TM{number}	Sets top margin to {number}	1
BM{number}	Sets bottom margin to {number}	1
PN{number}	Sets {number} of first page printed	1
PL{number}	Sets {number} of printed lines per page	58
PI{number}	Sets page interval (form length) to {number}	66
LI{number}	Sets {number} of spaces between lines	0
SP{0 or 1}	Selects continuous sheet feed {0} or single page {1} printing	0
PD{number}	Selects print device destination slot	1
CR{0 or 1}	Selects {1}/deselects {0} line feed signal to printer	0
LJ	Left justify	
FJ	Fill justify	LJ
CJ	Center justify	
RJ	Right justify	
TL	Specify top line headings	blank
BL	Specify bottom line headings	blank

The Print/Program commands and the commands which follow can be embedded in your text by preceding them with a carriage return and a period. Each text-embedded command must be entered on a separate line.

.FF	Form feed
.FF{number}	Conditional form feed if less than {number} lines left on page being printed
.IN{text}	Stops printing and displays {text} on monitor
.EP{0 or 1)	Suppresses {0} or enables {1} printing